


## Intuition-6 Email Report Settings


This document provides instructions on how to program the Email Report Settings so as to enable the controller to send user defined reports to recipients. Email Server options are included.

Log into the Intuition-6 controller using a computer. Go to the Config menu, then go to the Email Report Settings menu.




# Intuition-6 Email Report Settings

Click on Email Addresses to add Email Recipients




You can Add Up To 8 Email Recipients.




# Intuition-6 Email Report Settings

Setting up the Report Type – Click on Report #1 Inactive




Select Report Type

Options are **None/Alarm/Data Log/Graph/Summary**




# Intuition-6 Email Report Settings

For example, select Summary as the Report Type.




Then select Repetition. In this example, Daily is selected.



# Intuition-6 Email Report Settings

Make sure a Report Time is selected, and the Email Recipient(s) are checked off ✓



## Intuition-6 Email Report Settings

### Email Server Settings:

Select the type of email server to be used: Walchem Fluent®, SMTP, ASMTMP, or TLS/SSL.

The screenshot displays the 'Email Report Settings' interface for the 'Intuition-6 Controller WCT6'. The left sidebar contains navigation options: Home, Alarms, Inputs, Outputs, Config, Graphs, Notepad, Instruction Manual, Walchem Fluent, Walchem.com, and Admin Log Out. The main content area includes:

- Date:** 2022-Jan-06
- Time:** 07:23:10
- Report #1, #2, #3, #4:** Each has an 'Inactive' button.
- Email Addresses:** 1
- From Addr:** CT5 (highlighted with a red box)
- Send Email Test Report:** Confirm button
- Test Report Recipients:** #1 fsposato@walchem.com
- Email Server:** A dropdown menu (highlighted with a red box) showing 'Walchem Fluent' selected, with other options: SMTP, ASMTMP, and TLS/SSL.

The screen shot above shows Walchem Fluent has been selected as the Email Server. With this option, you can custom name the From Addr field. Only enter the portion of the address to be shown before the @ symbol. All emails will be from @ walchem-fluent.net. For example, in the above screen shot, the controller From Addr would be CT5@walchem-fluent.net.

## Intuition-6 Email Report Settings

Alternately, you could select SMTP, ASMTMP, or TLS/SSL. You will need to obtain the information for the fields outlined in red below, from the email server service provider. The screen shot below shows ASMTMP was selected as the Email Server.

The screenshot displays the 'Email Report Settings' interface for the 'Intuition-6 Controller WCT6'. The left sidebar contains navigation options: Home, Alarms, Inputs, Outputs, Config, Graphs, Notepad, Instruction Manual, Walchem Fluent, Walchem.com, and Admin Log Out. The main content area includes:

- Date:** 2022-Jan-06
- Time:** 08:32:33
- Report #1, #2, #3, #4:** Each has an 'Inactive' button.
- Email Addresses:** 1
- SMTP Server:** A text input field, highlighted in red.
- SMTP Port:** 587, highlighted in red.
- From Addr:** A text input field, highlighted in red.
- ASMTMP Username:** A text input field, highlighted in red.
- ASMTMP Password:** A text input field, highlighted in red.
- Send Email Test Report:** A 'Confirm' button.
- Test Report Recipients:** #1 fsposato@walchem.com
- Email Server:** A dropdown menu set to 'ASMTMP', highlighted in red, with an 'Edit' button.

**SMTP Server** Will not appear if Email Server is Walchem Fluent. Enter the SMTP server address, either numeric or its name.

**SMTP Port** Will not appear if Email Server is Walchem Fluent. Walchem Fluent email requires that port 49887 is open. Enter the port to be used by email server. The default is port 25 for SMTP, port 587 for ASMTMP, and port 465 for TLS/SSL.

**From Address** Enter the controller's email address. If the email server selected is Walchem Fluent, only enter the portion of the address to be shown before the @ symbol. All emails will be from @ walchem-fluent.net

**ASMTMP Username** Enter the username required for authentication. Only appears if the email server type is ASMTMP or TLS/SSL.

**ASMTMP Password** Enter the password required for authentication. Only appears if the email server type is ASMTMP or TLS/SSL.

# Intuition-6 Email Report Settings

## Controller Name and Location:

WALCHEM  
IWAQI America Inc.

**Intuition-6 Controller**  
WCT6  
CWT System

Home  
Alarms  
Inputs  
Outputs  
Config  
Graphs  
Notepad  
Instruction Manual  
Walchem Fluent  
Walchem.com  
Admin Log Out

Email Report Settings

Date: 2022-Jan-06  
Time: 08:32:33

Report #1: Inactive  
Report #2: Inactive  
Report #3: Inactive  
Report #4: Inactive

Email Addresses: 1  
SMTP Server: [Empty]  
SMTP Port: 587  
From Addr: [Empty]  
SMTP Username: [Empty]  
SMTP Password: [Empty]

Send Email Test Report: Confirm

Test Report Recipients: #1 fsposato@walchem.com

Email Server: ASMTTP [Edit]

You can also program a customer name and a custom location into the controller as shown in the red outlined area in the screen shot above.

To do this, go to the Config menu/Global Settings.

WALCHEM  
IWAQI America Inc.

**Intuition-6 Controller**  
WCT6  
CWT System

Home  
Alarms  
Inputs  
Outputs  
Config  
Global Settings  
Security Settings  
Ethernet Settings  
WiFi Settings

Global Settings

Date: 2022-Jan-06  
Time: 08:50:14

Date [YYYY - Mmm - DD]: 2022 - Jan - 06  
Time [HH:MM:SS]: 08 : 50 : 14  
Name: WCT9

Location: CWT System  
Global Units: Imperial  
Temperature Units: °F

Alarm Delay [MM:SS]: 00 : 00  
HVAC Modes: Enabled

Language: English [Edit]